

# Most Common Parameters

ingressOverrideSourceDomain	iosrcd
ingressOverrideDestinationDomain	iodstd
overrideDestinationDomain	odstd
overrideSourceDomain	osrcd

## ASM Adaptations

\*Adaptations are Case Sensitive\*

**fromto** The From and To headers are only modified by adaptation if the fromto module parameter is present and has the value of true. See Adaptation Module Administration below.

**adaptForeignURI** In Session Manager, Request-URI and To headers are not adapted on ingress if the host part of the URI is an IP address that is different from the IP address of the Session Manager. If required, the new adaptation module parameter adaptForeignURI can be added to provide the earlier adaptation behavior prior to that of Session Manager 6.2 release.

**keepPortTransport** All adaptations strip the port and transport from the Request-URI if the host-part is adapted on egress. This behavior can be overridden with the keepPortTransport parameter.

**multipartMIMEsupported** This option can be abbreviated to MIME. This option is applicable to egress processing only. If the parameter is set to no, the multipart MIME message bodies are stripped on egress from Session Manager. If the multipart MIME message contains an SDP message body, the message body will be inserted as the only message body in the outgoing message. If omitted or set to any other value, the message bodies will not be modified.

**adaptForeignURI** If the value is set to true, the INGRESS adaptation is applied to the Request-URI and to the header if the fromto parameter is set, even if the host part is an IP address that is different from the IP address of the Session Manager.

**noidtmf**: If the value is set to true, no DTMF message body conversion is performed on ingress.

**dtmf** The value of this parameter determines the DTMF message body format that is desired on egress from the Session Manager. If omitted, no conversion is done. Supported values are nortel, relay, and dtmf.

**keepPortTransport** If this parameter is present and set to any value, Session Manager does not strip the port and transport when the domain of the Request-URI is modified on egress.

**noar** This parameter requires a comma-separated list of SIP response codes. This parameter is applicable to the egress adaptation only. You can use this parameter to override the default alternate routing behavior of Session Manager. Session Manager does not alternate route a request to the next SIP Entity if it receives one of the responses listed in the parameter value. An example of a comma-separated list is noar = 404,486.

**sessionTimeout** Use this parameter for SIP entities that do not support the session timer, as per RFC 4028, or to send periodic SIP messages to keep the session active for more than one hour. If both

entities use the session timer in a call, Session Manager keeps the session active for the negotiated interval. If the entities do not use the session timer in a call, then Session Manager keeps the session active for one hour after the last SIP transaction. In such cases, you can set this parameter (in seconds) to extend the one hour interval. For example, if the session timer is not used, the parameter value of `sessionTimeout=7200` makes the session stay in memory for 7200 seconds (120 minutes) after the last SIP message exchange.

**noallow** This parameter requires a comma-separated list of SIP methods. The system strips the methods from the Allow header on egress. Method names are case-insensitive. For example, `noallow=UPDATE` and `noallow=UPDATE,OPTIONS`.

**iRHdrs** Remove the specified header or headers during adaptation process from messages in the ingress direction. Separate multiple headers with a comma. For example, `P-Charging-Vector,P-Location`. Header names are case-insensitive. The administrator can remove the headers that Session Manager may add during post adaptation module invocation, for example, `P-Location`.

**eRHdrs** Remove the specified header or headers during adaptation process from messages in the egress direction. Separate multiple headers with a comma. For example, `P-Charging-Vector,P-Location`. The administrator can remove the headers that Session Manager may add during post adaptation module invocation, for example, `P-Location`.

**reduceRtHdrs** The intermediate element adds routing headers when the SIP messages move from one element to other. To reduce the number of routing headers values from the SIP message, use the `reduceRtHdrs` parameter. If you set the value of `reduceRtHdrs` to true, the system reduces the number of routing headers values, such as `Via` and `Record-Route` from the SIP message. However, all the outgoing messages from Session Manager will have the `Via` and `Record-Route` header with values of Session Manager IP and transport so that all the responses and subsequent requests for that call can be delivered to Session Manager.

**reduceRtHdrs** The `reduceRtHdrs` parameter is introduced in Session Manager, to enable the Routing Header Compression feature.

**addRouteHdrs** This parameter adds the indicated Route headers to outgoing requests to the entity for dual-Route header support required by Assured Services SIP interface to SoftSwitch. The `addRouteHdrs` parameter is used in DOD networks to route calls between ESC and LSC utilizing SoftSwitch. The `addRouteHdrs` values must be added within quotation marks. Multiple values must be separated with a comma. For example  
“`<sip:10.129.177.129:5061;transport=tcp;lr>,<sip:10.133.177.129:5061;transport=tcp;lr>`”

## EGRESS Domain Modification parameters

The EGRESS Domain Modification parameters are:

**overrideDestinationDomain** ( can be abbreviated to `odstd`):By default, this is the first parameter. The Adaptation module replaces the domain in Request-URI, To header (if administered), Refer-To header, and Notify/message-summary body with the given value for egress only. If the request is a REFER, the domain in the Refer-To header will only be modified if it is the IP address of the Session Manager or a domain for which the Session Manager is authoritative.

**overrideSourceDomain** ( may be abbreviated to `osrcd`): The Adaptation module replaces the domain in the From header (if administered), P-Asserted-Identity header and calling part of the History-Info header with the given value for egress only. The Module Parameter:`osrcd=dr.avaya.com odstd=ny.avaya.com` is the same as the verbose form `overrideSourceDomain=dr.avaya.com`

overrideDestinationDomain=ny.avaya.com.

## INGRESS Domain Modification parameters

The INGRESS Domain Modification parameters are:

**ingressOverrideDestinationDomain** ( can be abbreviated to iodstd): Adaptation module replaces the domain in Request-URI, To header (if administered), and Notify/message-summary body with the given value for ingress only. If the request is a REFER, the domain in the Refer-To header will only be modified if it is the IP address of the Session Manager or a domain for which the Session Manager is authoritative.

**ingressOverrideSourceDomain** ( can be abbreviated to iosrcd): Adaptation module replaces the domain in the From header (if administered), P-Asserted-Identity header and calling part of the History-Info header with the given value for ingress only.

## EGRESS Display Name Modification

**egressDisplayName** : In Session Manager, if this parameter is present, the adaptation module modifies the display name of the Contact, P-Asserted-Identity, and From/To headers (if fromto = true is specified) of the egress messages.

For outgoing calls, the adaptation module applies the adaptation to the P-Asserted-Identity, Contact, and From headers in both the initial dialog-creating request sent from the Session Manager and in all subsequent in-dialog requests.

For incoming calls, the adaptation module applies the adaptation to the P-Asserted-Identity, Contact, and To headers. If the value of the parameter contains spaces, then the value must be enclosed in double quotes. Additionally, any double quotes that are part of the parameter value must be preceded by a backslash character.

Example values for the egressDisplayName parameter are:

egressDisplayName=SomeCallingName

egressDisplayName="My Business"

egressDisplayName="The \"Best\" Business"

From:

<https://wiki.buergi.org/> - **Reto's WIKI**

Permanent link:

<https://wiki.buergi.org/doku.php?id=avaya:asm:asmadaptation&rev=1721202889>

Last update: **2026/01/20 22:45**

